No IDENT : UG_DYLAU_18.0.0

IDENT. NR

DYMOLA LAUNCHER USER GUIDE

EDITION ISSUE

: 18.0.0

DATE : 17/12/2018

killPROJET ΑII

PROJECT

DYMOLA LAUNCHER

LOGICIEL SOFTWARE

VERSION 19.0.0

VERSION

	Department/Function	Nom / Name	Date	Signature
PREPARE PAR : PREPARED BY	DTP/RTEP/OS	ALTRAN SO	28/03/2019	
APPROUVE PAR : APPROVED BY	DTP/RTEP/OS	F. LEROY	28/03/2019	
ACCEPTE PAR : ACCEPTED BY	DTP/RTEP/OS			

DIFFUSION EXTERNE / EXTERNAL DISTRIBUTION: Yes

DIFFUSION INTERNE / INTERNAL DISTRIBUTION: No

DECLARATION DE PROPRIETE

Ce document ainsi que les informations qui y sont mentionnées, les plans séparés sy référant et édités avec ce document sont fourn is d'une façon confidentielle et sont la propriété de LIEBHERR-AEROSPACE TOULOUSE SAS.

Il ne doit pas être reproduit (en totalité ou partiellement) ou utilisé pour la fabrication ou encore divulgué sans avoir obtenu préalablement le consentement écrit de la Société.

PROPRIETARY DECLARATION
This document and the information contained herein, together with any separate drawings referred to and issued with this document, is supplied in confidence and is the property of LIEBHERR-AEROSPACE TOULOUSE SAS.

It must not be reproduced (in whole or in part) or used for manufacturing purpose, or otherwise disclosed, without the prior written consent of the company.

408 Av enue des Etats-Unis - 31016 TOULOUSE CEDEX - TEL. 33 (0)5.61.35.28.28 - FAX.33 (0)5.61.35.29.52

FORMULAIRE LTS-FRM-05-0088-1 Code OTAN: F1958

FICHIER User_Guide.doc

No IDENT.: DYMOLA LAUNCHER 18.0.0 EDITION: 19.0.0 PAGE: 2 IDENT. NR

ISSUE

TOTAL NUMBER OF PAGES: 13

REVISIONS RECORD

EDITION/ISSUE	DATE	MODIFICATIONS/REVISIONS
V19.0.0	03/04/2019	Initial version

NO IDENT. : DYMOLA LAUNCHER 18.0.0

3.5.4

3.5.5

REFERENCES

EXECUTION BUTTON: LAUNCH DY MOLA

IDENT. NR ISSUE SOMMAIRE/CONTENTS 1 INTRODUCTION 4 1.1 DOCUMENT PURPOSE 4 1.2 **TERMINOLOGY** 2 TOOL SETTING 2.1 GENERAL 5 5 2.2 **SETTINGS** 2.2.1 WORKSPACE ROOT 5 5 2.2.2 **BUSINESS PROFILES** 2.2.3 Logs 6 2.2.4 LANGUAGE 6 3 TOOL OVERVIEW 7 7 3.1 **M** AIN WINDOW 3.2 **M** AIN MENU 7 3.2.1 7 **FILE MENU** 8 3.2.2 **CONFIGURATION** 3.2.3 **SVN MENU** 8 3.2.4 HELP 9 MODE / TREE VIEW 9 3.3 3.4 SERVER MODE 10 3.4.1 TRUNK, TAGS, BRANCHES RADIO BUTTONS 10 LIST OF SELECTED SVN DIRECTORY (TRUNK, TAGS, BRANCHES) 3.4.2 11 3.4.3 11 INFORMATION PANEL 3.4.4 REFERENCES (VISUALIZATION ONLY) 11 3.4.5 EXECUTION BUTTON: DOWNLOAD 11 3.5 LOCAL MODE 11 3.5.1 TRUNK, TAGS, BRANCHES RADIO BUTTONS 12 3.5.2 LIST OF SELECTED SVN DIRECTORY (TRUNK, TAGS, BRANCHES) 12 3.5.3 INFORMATION PANEL 13

EDITION: 19.0.0

PAGE: 3

13

13

NO IDENT.: DYMOLA LAUNCHER 18.0.0 EDITION: 19.0.0 PAGE: 4

ISSUE

1 INTRODUCTION

IDENT. NR

1.1 DOCUMENT PURPOSE

This document is the user guide of DYMOLA LAUNCHER application.

The MUSE application allows to launch simulations on one or many flight case and to display the results in different forms (reports, table and graphs)

1.2 TERMINOLOGY

Abbreviation	Description
LTS	Liebherr Aerospace Toulouse
SI	International System of units
<dymola_launcher< th=""><th>Application installation root path</th></dymola_launcher<>	Application installation root path
ROOT>	(by default: C:\LTS\OUTILS\DYMOLA_LAUNCHER)

NO IDENT.: DYMOLA LAUNCHER 18.0.0 EDITION: 19.0.0 PAGE: 5


IDENT. NR ISSUE

2 TOOL SETTING

2.1 GENERAL

Applications general settings are gathered in a text file which format is xml.

This file, named Dymola launcher.exe.config is located in the directory: <DYMOLA_LAUNCHER ROOT>\bin.



Before launching the application, general settings can be configured using a text editor.

2.2 SETTINGS

2.2.1 WORKSPACE ROOT

The setting « WORKSPACE » is used to define the workspace root path where projects are stored.

This setting value can be modified to change project workspace root path.

2.2.2 BUSINESS PROFILES

<string>Statique,StaticSystems,https://ltssvn/OS/generic/DYMOLA_LAUNCHER/WO RKSPACE/StaticSystems

<string>Dynamique,DynamicSystems,https://ltssvn/OS/generic/DYMOLA_LAUNCH ER/WORKSPACE/DynamicSystems</string>

```
<string>Valves, ValveSystems, https://ltssvn/OS/generic/DYMOLA_LAUNCHER/WORKSPACE/ValveSystems</string>
    </ArrayOfString>
    </value>
    </setting>
```

No IDENT.: DYMOLA LAUNCHER 18.0.0 EDITION: 19.0.0 PAGE: 6

IDENT. NR ISSUE

The setting Business profiles is used to define the business profiles used in Dymola Launcher. Theses Business profiles contains a Svn path and an Alias for the business name.

2.2.3 LOGS

The log folder is stored in <DYMOLA_LAUNCHER ROOT>\Log\log.txt.

2.2.4 LANGUAGE

The setting « LANGUAGE » is used to configure the DYMOLA LAUNCHER application language.

Two values are available:


- "English"
- "French".

No Ident.: DYMOLA LAUNCHER 18.0.0 EDITION: 19.0.0 PAGE: 7

IDENT. NR ISSUE

3 TOOL OVERVIEW

3.1 MAIN WINDOW



The main window is composed of four main parts:

- (1): the main menu
- (2): the project Mode
- (3): the Tree (Server or Local)
- (4): the result frame

3.2 MAIN MENU

3.2.1 FILE MENU


No Ident.: DYMOLA LAUNCHER 18.0.0 EDITION: 19.0.0 PAGE: 8

IDENT. NR ISSUE



The File menu contain a menu item Exit. When cliqued, the application is existed, the current state of the application is saved.


3.2.2 CONFIGURATION



This configuration menu have two menu items:

- Business profile: open a window with a the list of business profile.
- Librairies update: launch the update process. When clicked a progress bar cycles. An alert window pops up at the end of the operation

3.2.3 SVN MENU



This menu lists the possible Svn commands. When selected, they open a Tortoise svn windows. The possible actions are :

- Update
- Commit
- Create branch
- Tag the trunk

No IDENT.: DYMOLA LAUNCHER 18.0.0 EDITION: 19.0.0 PAGE: 9

IDENT. NR ISSUE

3.2.4 HELP




This menu contains the usual User guide and about menu item.

- User guide open this pdf
- About shows a windows with the Liebherr copyright informations.

3.3 MODE / TREE VIEW

The mode is associated to the Tree view. When changed, the application swaps between the informations stored in the Svn server path, or the local workspace. Those path are stored in the business profile and in the workspace parameter.

MODE




No IDENT.: DYMOLA LAUNCHER 18.0.0 EDITION: 19.0.0 PAGE: 10

IDENT. NR ISSUE

3.4 SERVER MODE

In the Server part the result frame is divided in three parts:

- (1): Trunk, Tags, Branches radio buttons
- (2): List of selected svn directory (Trunk, Tags, Branches)
- (3): Information panel
- (4): References (visualization only)
- (5): Execution buttons



3.4.1 TRUNK, TAGS, BRANCHES RADIO BUTTONS

A radio button to choose between the svn:

• Trunk

No IDENT.: DYMOLA LAUNCHER 18.0.0 EDITION: 19.0.0 PAGE: 11

IDENT. NR ISSUE

- Tags
- Branch

3.4.2 LIST OF SELECTED SVN DIRECTORY (TRUNK, TAGS, BRANCHES)

Show the list of project contained in the selected Svn main folder.

3.4.3 INFORMATION PANEL

Lists the information about the Svn project

3.4.4 REFERENCES (VISUALIZATION ONLY)

Show the references attached to the currently selected project. The references cannot be selected or checked in this mode

3.4.5 EXECUTION BUTTON: DOWNLOAD

When clicked, this button start the download operation, of the currently selected project with it's references.

- If the downloaded project exist, a confirmation is asked.
- If the downloaded references associated to the project exists, a confirmation is asked.

3.5 LOCAL MODE

The local mode shows a view of the folders located in the workspace location. This location can be defined in the settings of the application.


The application swaps automatically to this mode after a folder have been selected.

In the Server part the result frame is divided in three parts:

- (1): Trunk, Tags, Branches radio buttons
- (2): List of selected svn directory (Trunk, Tags, Branches)
- (3): Information panel, with select for library and
- (4): References
- (5): SVN Buttons
- (6): Launch Dymola

No IDENT.: DYMOLA LAUNCHER 18.0.0 EDITION: 19.0.0 PAGE: 12

IDENT. NR ISSUE



3.5.1 TRUNK, TAGS, BRANCHES RADIO BUTTONS

A radio button to choose between the svn:

- Trunk
- Tags
- Branch

3.5.2 LIST OF SELECTED SVN DIRECTORY (TRUNK, TAGS, BRANCHES)


Show the list of project contained in the selected svn main folder.

No Ident.: DYMOLA LAUNCHER 18.0.0 EDITION: 19.0.0 PAGE: 13

IDENT. NR ISSUE

3.5.3 INFORMATION PANEL

Lists the information about the local workspace project.



Beside displaying informations about the model, this panel allow the user to choose with two combo box:

- The Library version: stored on the Network
- The Dymola version : search on the local computer the availables version of Dymola.

3.5.4 REFERENCES

Show the references attached to the currently selected project. The references cannot be selected or checked in this mode.



There's two buttons associated to the references:

- Add: A windows popup to associate a reference to the current project
- Remove: Remove an associated reference.

3.5.5 EXECUTION BUTTON: LAUNCH DYMOLA

This button launch Dymola.

- Generate a script with the selected Dymola informations.
- Launch an instance of Dymola in a new process, Dymola Launcher remain available during the execution